## SIT RD Gateway Connection for Microsoft Windows School of Information Technology, KMUTT.

## Step for Microsoft Windows

- 1. Open Remote Desktop Connection.
- 2. Click Show Options if it hide.

Nemote D	esktop Connection	_			$\times$
	Remote Desktop <b>Connection</b>				
Computer:	Example: computer.fabrikam.com		~		
User name:	None specified				
The computer name field is blank. Enter a full remote computer name.					
Show Op	tions	Connect		Help	

3. Click tab **Advanced** then in Connect from anywhere click **Settings**.

\rm Remote	Desktop Connection			×
	Remote Desktop Connection			
General Dis				
9	Server authentication verifies that y intended remote computer. The stu required to connect is determined If server authentication fails:	rength of the verificat	ion	
	Warn me		×	
Connect fr	om anywhere Configure settings to connect throu when I am working remotely. Settings	ugh Remote Desktop	Gateway	
A Hide Op	tions	Connect	Help	

4. In RD Gateway Setting check **Use these RD Gateway server settings** and fill Server name with **rdp.sit.kmutt.ac.th** then click **OK**.

ND Gateway Server Settings	×
Remote Deskt	
Connection settings Automatically detect RD Gateway Use these RD Gateway server set	
Server name: rdp.sit.km	
Logon method: Allow me	to select later
✓ Bypass RD Gateway server for ○ Do not use an RD Gateway server	
Logon settings	
User name: None specified	
You will be asked for credentials whe server.	n you connect to this RD Gateway
Use my RD Gateway credentials fo	or the remote computer
	OK Cancel

- 5. Click tab **General**.
  - a. fill Computer with VMname as your lecturer gave and add .ad.sit.kmutt.ac.th example s642int670v041.ad.sit.kmutt.ac.th.
  - b. fill User name with VMname\VMuser as your lecturer gave example s642int670v041\Administrator.
  - c. Click **Connect**.

Nemote	Desktop Connectio	n	-		$\times$
	Remote De Connect				
General Dis Logon sett	Ings Enter the name of the nam	es Experience Advar ne remote computer. Name.ad.sit.kmutt.ac.th name\VMUser r credentials when you	h	~ 	
		nnection settings to an		pen a ⊃ <u>e</u> n	
A Hide Op	tions		Co <u>n</u> nect	Help	2

6. In RD Gateway Sever Credentials use ad\StudentID as username and use your email password for password then click OK.

Windows Security	×	
RD Gateway Server Credentials		
Enter your credentials to connect to rdp.sit.kmutt.ac.th		
ad\รหัสนักศึกษา		
Password		
Domain: ad		
Remember me		
ОК	Cancel	

7. Fill **VM password** as your lecturer gave then click **OK**.

Windows Security	×	
Enter your credentials		
These credentials will be used to connect to s642int670v041.ad.sit.kmutt.ac.th.		
s642int670v041\Administrator		
Password		
Remember me		
More choices		
OK Cancel		

8. Click **Yes** for accept certificate of VM.

Nem 😽	note Desktop Connection	×
	The identity of the remote computer cannot be verified. Do you want to connect anyway?	ı
	note computer could not be authenticated due to problems with its / certificate. It may be unsafe to proceed.	
Certific	cate name	
	Name in the certificate from the remote computer: S642INT670V041.ad.sit.kmutt.ac.th	
Certific	cate errors	
	following errors were encountered while validating the remote puter's certificate:	
<u>^</u>	The certificate is not from a trusted certifying authority.	
Do you	want to connect despite these certificate errors?	
Don	't ask me again for connections to this computer	
View	v certificate Yes No	

## 9. Done. You are on your VM.



10. If you want to disconnect from VM just close the VM windows.

## Infrastructure, SIT

Email : servicedesk@sit.kmutt.ac.th

Tel.: 02-470-9878

Microsoft Team : wuttichai.pae@kmutt.ac.th

Update by Wuttichai Paewwat